BLUE WATERS SUSTAINED PETASCALE COMPUTING

Running Jobs on Blue Waters

Jing Li, Omar Padron























Jobs on Blue Waters

- Jobs on Blue Waters are managed through the use of:
 - Resource manager: TORQUE
 - Workload manager: Moab
- Commands for managing jobs on Blue Waters are a subset of PBS (Portable Batch System) commands.
- Application launcher (aprun) utility launches applications on compute nodes.
- Application Level Placement Scheduler (ALPS) handles application placement and execution.













Jobs on Blue Waters

- Two type of jobs interactive and batch
- Interactive mode for debug and optimization
- Batch mode for normal job runs
- Steps for setting up a job:
 - Determine the resources needed
 - > Pick a queue that will provide the required resources
 - Create a PBS job script that includes the aprun command and describes the resources needed
 - Submit the job script to the batch system using qsub













Submit Jobs

- Interactive jobs
 qsub -I -l nodes=1
 qsub -I -l nodes=2:ppn=32:xe -l
 walltime=01:00:00
- Batch jobsqsub my_script.pbs













PBS Script

- Sample scripts are at /sw/userdoc/samplescripts
- Extensive discussion in Documentation on Blue Waters Portal
- PBS scripts
 - Specify resource needed
 - Provide file names for stdout and stderr
 - Define environmental variables
 - Load needed modules
 - Launch the job via the aprun command













PBS Script - Resources and Notification

```
#PBS -l nodes=2048:ppn=32:xe
#PBS -l walltime=01:20:00
#PBS -N testjob
#PBS -e $PBS_JOBID.err
#PBS -o $PBS_JOBID.out
#PBS -m bea
#PBS -M username@host
```













PBS Script - Others

- cd \$PBS_O_WORKDIR
 - > By default, job starts at \$HOME, your home directory
 - Often it is desirable that job starts where batch job is submitted, which is in \$PBS_O_WORKDIR
 - Excutables used, input and output files can come from and go to directories of choice
- module load your_modules
 - module load craype-hugepages2M
- export your_environment_variables
 - > export OMP_NUM_THREAD = 2
- aprun -n 65536 ./app.exe < in > out.\$PBS_JOBID













PBS Script – Simple Example

```
#!/bin/bash
#PBS -1 nodes=2:ppn=32:xe
#PBS -1 walltime=00:30:00
#PBS -N testjob
. /opt/modules/default/init/bash
module swap PrgEnv-cray PrgEnv-gnu
cd $PBS O WORKDIR
aprun -n 64 ./app.exe < input.dat > output.out
```













Submit and Manage Jobs

- qsub submit job
 qsub -I -l nodes=2:ppn=32:xe -l walltime=01:00:00
 qsub my_script.pbs
- qstat check job status
 qstat
 qstat | grep -i john
- qdel remove a job
 qdel job_id













Aprun options

- -n: Number of processing elements PEs for the application
- -N: Number of PEs to place per node
- -S: Number of PEs to place per NUMA node.
- -d: Number of CPU cores required for each PE and its threads
- -cc: Binds PEs to CPU cores.
- -r: Number of CPU cores to be used for core specialization
- -ss: Enables strict memory containment per NUMA node













Aprun - basics

MPI runs for 8 and 64 MPI's:

```
aprun —n 8 a.out (Needs 1 node.) aprun —n 64 a.out (Needs 2 nodes.)
```

 MPI + openMP runs for 4 MPI's each having two openMP threads, and 16 MPI's each having 4 threads:

```
aprun —n 4 —d 2 a.out (Needs 1 node.) aprun —n 16 —d 4 a.out (Needs 2 nodes.)
```













Aprun - advanced

MPI runs

```
aprun —n 8 —S 2 a.out (Needs 1 node, Uses 4 NUNA.)

aprun —n 64 —N 16 —S 4 a.out (Needs 4 node, Uses 4 NUNA.)

aprun —n 64 —cc 0,2,4,6,8,10,12,14,16,18,20,22,24,26,28,30 a.out (Needs 4 node, Uses 4 NUNA.)
```

MPI + openMP runs

```
aprun -n 4 -S 1 -d 2 a.out (Needs 1 node, Uses 4 NUNA.)

aprun -n 16 -N 4 -S 1 -d 4 a.out (Needs 4 node, Uses 4 NUNA.)

aprun -n 32 -d 2 -cc 0,2:4,6:8,10:12,14:16,18:20,2:24,26:28,30

a.out (Needs 4 node, Uses 4 NUNA.)
```













Aprun - advanced

- -cc specifies which cores to use on a node by a job.
- ``:" sperates a PE and its threads from other PE's and their threads.
- -ss restricts a PE's memory use to NUMA-local memory only.
- r sets aside one or more cores for OS services.













Multiple apruns – Run Sequentially

- A series of aprun's, running one after the other aprun -n 32 ./a.out aprun -n 64 ./b.out aprun -n 16 ./c.out
- Request resource accordingly #PBS –I nodes=2













Mupltiple aprun's – Run Concurrently

Runs simultaneously – important to ``wait"

```
aprun -n 32 ./a.out & aprun -n 64 ./b.out & aprun -n 16 ./c.out & wait
```

Request resource accordingly

```
#PBS -l node=4
```













Mupltiple apruns – MPMD

- MPMD
 aprun -n 256 ./a.out : -n 768 ./b.out
- Executables share MPI COMM WORLD
- Nodes needed #PBS –I nodes=32

Note, there can be no more than one set of aprun arguments per node.











Single and Dual Stream

- Single place one PE on one floating point unit (FPU)
- Daul place one PE on one integer core, two PE's share a FPU, the default
- Considerations the amount of floating point operations in the application, the amount of memory needed per PE











Queues and charging

BLUE WATERS

Queue	Priority	Changing Factor
debug	1	1
high	2	2
normal	3	1
low	4	0.5

Note: low queue jobs are preemptable - subject to early termination by the scheduler.













Batch job stderr/stdout

- Redirect application stdout/stderr to a file (preferably on scratch) rather than letting the batch software capture it.
 - > cd /scratch/...
 - > aprun -n ... > outerr.\$PBS_JOBID 2>&1 (bash)
- Easier to track job progress.
- Avoid excessive stdout and stderr from applications as task count increases. Consider reporting by rank 0 or a few ranks.











File Systems

- There are three file systems: /u, /project, and /scratch.
- Scratch is the largest and fastest (1440 OSTs). Jobs should be launched from scratch.
- All three file systems are visible from compute nodes.
- Purging of scratch will be threshold based with a 2 week age based policy.
- Current issue limits stripe count to 160 OSTs.
- For a single OST, there is a 2 TB file limit.
- More in the I/O talk later in the workshop.












Setting Process Affinity – BW XE node



- 32 integer cores
- 16 FPU's
- 4 NUMA nodes
- 2 sockets













Setting Process Affinity – pure MPI code

Assume XE nodes are used, then:

- aprun -n 64
 It places 32 mpi processes on a XE node by default. Needs 2 nodes.
- aprun -n 64 -N 8
 It places 8 mpi processes on a XE node. However by default, all 8 processes will be on 1 NUMA node. Needs 8 nodes.
- aprun -n 64 -N 8 -S 2
 It places 8 mpi processes on a XE node using all 4 NUMA nodes with 2 mpi processes per NUMA. Needs 8 nodes.













Setting Process Affinity – pure MPI code

Assume XE nodes are used in the following. The -cc option provides precise control on placements:

- aprun -n 64 -N 8 -cc 0,1,8,9,16,17,24,25
 It specifies actually where each of 8 mpi processes on a node will be placed. Needs 8 nodes.
- aprun -n 64 -N 8 -cc 0,4,8,12,16,20,24,28
 It specifies a different placement compared to the above. Needs 8 nodes.













Setting Process Affinity – MPI+openMP

Assume XE nodes are used, then:

- ``aprun -n 32 —d 2"
 It places 16 mpi processes on a XE node by default. Each mpi has 2 threads. (Needs 2 nodes.)
- ``aprun -n 32 -N 8 -d 2"
 It places 8 mpi processes on a XE node, each with 2 threads. However by default, all 8 processes will be on 1 socket. (Needs 4 nodes.)
- ``aprun -n 32 -N 8 -S 2 —d 2"
 It places 8 mpi processes on a XE node, 2 on each NUMA using all 4 NUMA nodes (i.e. 2 sockets). Each mpi again has two threads. (Needs 4 nodes.)













Setting Process Affinity – MPI+openMP

Assume XE nodes are used. The -cc option provides precise control on placements:

- aprun -n 64 -cc 0,1:2,3:8,9:10,11:16,17:18,19:24,25:26,27 It puts 8 mpi processes on an XE node, with core 0,1 for 1st process and its 2 threads; core 2,3 for 2nd process and its 2 threads ... 4 nodes are needed.
- aprun -n 64 -cc 0,1:4,5:8,9:12,13:16,17:20,21:24,25:28,29 It puts 8 mpi processes on an XE node, with core 0,1 for 1st process and its 2 threads; core 4,5 for 2nd process and its 2 threads ... 4 nodes are needed.













Blue Waters XE Node

Bulldozer














Each "Integer Unit" is an aprun "CPU"















Each "Integer Unit" is an aprun "CPU"














Red dashed outline is "NUMA node"
















Default placement by aprun -n 8














aprun -n 8 -S 4















aprun –n 8 –d 2
















aprun -n 8 -cc 0,2,4,6,8,10,12,14















Managing and monitoring jobs

System commands

- qstat, qdel, showq, showres torque and moab
- apstat, xtnodestat alps

Scripts

- qpeek look at job stdout/stderr
- apstat_system.pl displays system status by node type
- qstat.pl displays qstat output with node type and count
- showqgpu.pl displays only XK jobs similar to showq













Why is my job not running?

- Make sure job was submitted the way you expected: qstat —f JOBID
 - > We employ a qsub filter that attempts to catch improperly configured requests.
- Check to see what is running with showq as eligible jobs are listed in a prioritized order. Using the '-i' option will show priority.
- Use 'checkjob JOBID' to see more about the job.
- Currently have a 300 second allocation cycle.













Common errors and error messages

- **OOM killer terminated this process**. This error message results when your application exceeds the available memory on a node.
- Claim exceeds reservation's node-count. This error message results when the combination of PBS nodes and aprun options (for example, -N, -S, -ss, -sn, -m) requires more nodes than were reserved for you by the qsub command.).













Programming Environment

- Use the module command to manage programming environment
- Paths, libraries, etc, will be properly set once a programing environment is set, e.g. module load PrgEnv-pgi
- Compiler wrappers ftn, cc, CC, etc, will use the corresponding compilers, the correct include files, and library paths.